



How To Install Nginx on Ubuntu 20.04

Introduction

[Nginx](#) is one of the most popular web servers in the world and is responsible for hosting some of the largest and highest-traffic sites on the internet. It is a lightweight choice that can be used as either a web server or reverse proxy. In this guide, we'll discuss how to install Nginx on your Ubuntu 20.04 server, adjust the firewall, manage the Nginx process, and set up server blocks for hosting more than one domain from a single server.

Prerequisites

Before you begin this guide, you should have a regular, non-root user with sudo privileges configured on your server. When you have an account available, log in as your non-root user to begin.

Step 1 – Installing Nginx

Because Nginx is available in Ubuntu's default repositories, it is possible to install it from these repositories using the **apt** packaging system.

Since this is our first interaction with the **apt** packaging system in this session, we will update our local package index so that we have access to the most recent package listings.

Afterwards, we can install **nginx**:

```
sudo apt update
sudo apt install nginx
```

After accepting the procedure, **apt** will install Nginx and any required dependencies to your server.

Step 2 – Adjusting the Firewall

Before testing Nginx, the firewall software needs to be adjusted to allow access to the service. Nginx registers itself as a service with **ufw** upon installation, making it straightforward to allow Nginx access.

List the application configurations that **ufw** knows how to work with by typing:

```
sudo ufw app list
```

You should get a listing of the application profiles:

```
Available applications:
Nginx Full
Nginx HTTP
Nginx HTTPS
```

As demonstrated by the output, there are three profiles available for Nginx:

- **Nginx Full:** This profile opens both port 80 (normal, unencrypted web traffic) and port 443 (TLS/SSL encrypted traffic)
- **Nginx HTTP:** This profile opens only port 80 (normal, unencrypted web traffic)
- **Nginx HTTPS:** This profile opens only port 443 (TLS/SSL encrypted traffic)

It is recommended that you enable the most restrictive profile that will still allow the traffic you've configured. Right now, we will only need to allow traffic on port 80.

You can enable this by typing:

```
sudo ufw allow "Nginx HTTP"
```

You can verify the change by typing:

```
sudo ufw status
```

The output will indicate which HTTP traffic is allowed:

```
Status: active

To          Action    From
--          -
OpenSSH    ALLOW    Anywhere
Nginx HTTP ALLOW    Anywhere
OpenSSH (v6) ALLOW    Anywhere (v6)
Nginx HTTP (v6) ALLOW    Anywhere (v6)
```

Step 3 – Checking your Web Server

At the end of the installation process, Ubuntu 20.04 starts Nginx. The web server should already be up and running.

We can check with the **systemd** init system to make sure the service is running by typing:

```
sudo systemctl status nginx
● nginx.service - A high performance web server and a reverse proxy server
   Loaded: loaded (/lib/systemd/system/nginx.service; enabled; vendor preset: enabled)
   Active: active (running) since Fri 2020-04-20 16:08:19 UTC; 3 days ago
     Docs: man:nginx(8)
   Main PID: 2369 (nginx)
    Tasks: 2 (limit: 1153)
   Memory: 3.5M
   CGroup: /system.slice/nginx.service
           └─2369 nginx: master process /usr/sbin/nginx -g daemon on;
             master_process on;
           └─2380 nginx: worker process
```

As confirmed by this output, the service has started successfully. However, the best way to test this is to actually request a page from Nginx.

You can access the default Nginx landing page to confirm that the software is running properly by navigating to your server's IP address. If you do not know your server's IP address, you can find it by using the icanhazip.com tool, which will give you your public IP address as received from another location on the internet:

```
curl -4 icanhazip.com
```

When you have your server's IP address, enter it into your browser's address bar:

```
http://your_server_ip
```

You should receive the default Nginx landing page:

Welcome to nginx!

If you see this page, the nginx web server is successfully installed and working. Further configuration is required.

For online documentation and support please refer to nginx.org. Commercial support is available at nginx.com.

Thank you for using nginx.

If you are on this page, your server is running correctly and is ready to be managed.

Step 4 – Managing the Nginx Process

Now that you have your web server up and running, let's review some basic management commands.

To stop your web server, type:

```
sudo systemctl stop nginx
```

To start the web server when it is stopped, type:

```
sudo systemctl start nginx
```

To stop and then start the service again, type:

```
sudo systemctl restart nginx
```

If you are only making configuration changes, Nginx can often reload without dropping connections. To do this, type:

```
sudo systemctl reload nginx
```

By default, Nginx is configured to start automatically when the server boots. If this is not what you want, you can disable this behavior by typing:

```
sudo systemctl disable nginx
```

To re-enable the service to start up at boot, you can type:

```
sudo systemctl enable nginx
```

You have now learned basic management commands and should be ready to configure the site to host more than one domain.

Step 5 – Setting Up Server Blocks (Recommended)

When using the Nginx web server, server blocks (similar to virtual hosts in Apache) can be used to encapsulate configuration details and host more than one domain from a single server. We will set up a domain called **your_domain**, but you should **replace this with your own domain name**.

Nginx on Ubuntu 20.04 has one server block enabled by default that is configured to serve documents out of a directory at **/var/www/html**. While this works well for a single site, it can become unwieldy if you are hosting multiple sites. Instead of modifying **/var/www/html**, let's create a directory structure within **/var/www** for our **your_domain** site, leaving **/var/www/html** in place as the default directory to be served if a client request doesn't match any other sites.

Create the directory for **your_domain** as follows, using the **-p** flag to create any necessary parent directories:

```
sudo mkdir -p /var/www/your_domain/html
```

Next, assign ownership of the directory with the **\$USER** environment variable:

```
sudo chown -R $USER:$USER /var/www/your_domain/html
```

The permissions of your web roots should be correct if you haven't modified your **umask** value, which sets default file permissions. To ensure that your permissions are correct and allow the owner to read, write, and execute the files while granting only read and execute permissions to groups and others, you can input the following command:

```
sudo chmod -R 755 /var/www/your_domain
```

Next, create a sample **index.html** page using **nano** or your favorite editor:

```
nano /var/www/your_domain/html/index.html
```

Inside, add the following sample HTML:

```
<html>
  <head>
    <title>Welcome to your_domain!</title>
  </head>
  <body>
    <h1>Success! The your_domain server block is working!</h1>
  </body>
</html>
```

Save and close the file by typing **CTRL** and **X** then **Y** and **ENTER** when you are finished.

In order for Nginx to serve this content, it's necessary to create a server block with the correct directives. Instead of modifying the default configuration file directly, let's make a new one at **/etc/nginx/sites-available/your_domain**:

```
sudo nano /etc/nginx/sites-available/your_domain
```

Paste in the following configuration block, which is similar to the default, but updated for our new directory and domain name:

```
server {
    listen 80;
    listen [::]:80;

    root /var/www/your_domain/html;
    index index.html index.htm index.nginx-debian.html;

    server_name your_domain www.your_domain;

    location / {
        try_files $uri $uri/ =404;
    }
}
```

Notice that we've updated the **root** configuration to our new directory, and the **server_name** to our domain name.

Next, let's enable the file by creating a link from it to the **sites_enabled** directory, which Nginx reads from during startup:

```
sudo ln -s /etc/nginx/sites-available/your_domain /etc/nginx/sites-enabled/
```

Two server blocks are now enabled and configured to respond to requests based on their **listen** and **server_name** directives:

- **your_domain**: Will respond to requests for **your_domain** and **www.your_domain**.
- **default**: Will respond to any requests on port 80 that do not match the other two blocks.

To avoid a possible hash bucket memory problem that can arise from adding additional server names, it is necessary to adjust a single value in the **/etc/nginx/nginx.conf** file. Open the file:

```
sudo nano /etc/nginx/nginx.conf
```

Find the **server_names_hash_bucket_size** directive and remove the **#** symbol to uncomment the line. If you are using nano, you can quickly search for words in the file by pressing **CTRL** and **w**.

```
...
```

```
http {
  ...
  server_name_hash_bucket_size 64;
  ...
}
...
```

Save and close the file when you are finished.

Next, test to make sure that there are no syntax errors in any of your Nginx files:

```
sudo nginx -t
```

If there aren't any problems, restart Nginx to enable your changes:

```
sudo systemctl restart nginx
```

Nginx should now be serving your domain name. You can test this by navigating to **http://your_domain**, where you should see something like this:

Success! The example.com server block is working!

Step 6 – Getting Familiar with Important Nginx Files and Directories

Now that you know how to manage the Nginx service itself, you should take a few minutes to familiarize yourself with a few important directories and files.

Content

- **/var/www/html**: The actual web content, which by default only consists of the default Nginx page you saw earlier, is served out of the **/var/www/html** directory. This can be changed by altering Nginx configuration files.

Server Configuration

- **/etc/nginx**: The Nginx configuration directory. All of the Nginx configuration files reside here.
- **/etc/nginx/nginx.conf**: The main Nginx configuration file. This can be modified to make changes to the Nginx global configuration.
- **/etc/nginx/sites-available/**: The directory where per-site server blocks can be stored. Nginx will not use the configuration files found in this directory unless they are linked to the **sites-enabled** directory. Typically, all server block configuration is done in this directory, and then enabled by linking to the other directory.
- **/etc/nginx/sites-enabled/**: The directory where enabled per-site server blocks are stored. Typically, these are created by linking to configuration files found in the **sites-available** directory.
- **/etc/nginx/snippets**: This directory contains configuration fragments that can be included elsewhere in the Nginx configuration. Potentially repeatable configuration segments are good candidates for refactoring into snippets.

Server Logs

- **/var/log/nginx/access.log**: Every request to your web server is recorded in this log file unless Nginx is configured to do otherwise.
- **/var/log/nginx/error.log**: Any Nginx errors will be recorded in this log.

DOWNLOAD AS PDF

Join The Conversation

Please [Log In](#) to post.

